

Recommended Settings

Go to your e107 administration area.


Settings/Images

1. Enable image posting
2. Enable Sleight

Plugins/Lightbox (if available)

1. Thumb - Right margin (used only if is set image_float parameter) - Set to 10
2. Thumb - Top margin (used only if is set image_float parameter) - Set to 5
3. Thumb - Bottom margin (used only if is set image_float parameter) - Set to 5

How to change Site Name



You can find all needed source files in folder "_sources" in the downloaded ZIP package.

From directory "_fonts" install all first

You can easy edit these two images. Use "header.psd" file from **directory "_sources"** The only thing you need to know is not to resize the images, just edit there contents.

1. Install all fonts from directory "_sources/fonts"
2. Open "header.psd" directory "_sources"




3. Double click on the text layer. Type your site name



7. Use arrow keys to adjust the text to the left or right

7. When you are done choose in Photoshop **File -> Save For Web** or press **Alt+Shift+Ctrl+S**



8. Click **"Save"** and navigate to **"SITEROOT/e107_themes/harmony/images"** and save as **"header.png"**.

9. Done

How switch menu bars



A. With "Corllete Lab User Style" plugin


If you have our plugin "Corllete Lab User Style" installed you can switch between this 3 views.

1. Go to the administration in your site
2. Choose **Plugins -> Corllete Lab User Style**
3. In the "Plugin Settings" section from the dropdown list for "Default style" set one of the 3 views.
4. Done
5. If you wish your visitors to switch the style you can enable "user_style_links" menu from **Content -> Menus**

B. Without "Corllete Lab User Style" plugin

If you don't have our plugin "Corllete Lab User Style" installed go to your administration area

1. Choose Tools -> Theme manager and set the default style



Display images in your flash header

You can display unlimited number of images

1. Resize your images to:
Width: 570px
Height: 245px
2. Upload your images to
SITEROOT/e107_themes/harmony/flash/pics
3. Enjoy your header! The rest is automatic done from .swf file

Disable flash header

1. Open

`SITEROOT/e107_themes/harmony/theme.php`

2. Search for:

```
define("FLASH_HEADER", TRUE);
```

3. Replace with

```
define("FLASH_HEADER", FALSE);
```

4. Done !

Feel free to contact us for more questions at
support@free-source.net

Copyright © 2006-2008 Corllete Ltd. All Rights Reserved.
Corllete is Reserved Trade Mark of Corllete Ltd.
Free-Source.net is a part of Corllete Ltd Group.